

Start by opening a web browser (Firefox or Internet Explorer) and typing in the link bar 192.168.1.1

Your web browser will then bring up a dialog box asking for username and password. You will leave the username field blank and type in the password field "admin" (without parenthesis).

The next screen you will see will look something like below. Start by clicking the Wireless tab then it should look very similar. Highlighted in red is link you should click next, "Wireless Security".

The screenshot shows the Linksys configuration interface for a RangePlus Wireless Router (WRT110). The top navigation bar includes the Linksys logo, the router model name, and the firmware version (1.0.03). The main navigation menu has tabs for Setup, Wireless, Security, Access Restrictions, Applications & Gaming, Administration, and Status. Under the Wireless tab, there are sub-links for Basic Wireless Settings, Wireless Security (highlighted in red), Wireless MAC Filter, and Advanced Wireless Settings. The Basic Wireless Settings section is currently active, showing fields for Network Mode (Mixed), Network Name (SSID), Radio Band (Auto - 20/40MHz Channel), Wide Channel (Auto), Standard Channel (Auto), and SSID Broadcast (Enabled). A Help... link is visible on the right side. At the bottom, there are buttons for Save Settings and Cancel Changes, along with the Cisco logo.

After the “Wireless Security” link is clicked this screen should be the one you see. In the highlighted red field will be your wireless security key needed for connecting wireless PCs to your network. Enter this key in where it is needed by your Wireless PC. Once you’ve retrieved your wireless key from the passphrase field please close your browser without saving any settings.

The screenshot displays the 'Wireless Security' configuration page for a RangePlus Wireless router. The page has a blue header with the title 'RangePlus Wireless' and a navigation menu with tabs for 'Setup', 'Wireless', 'Security', 'Access Restrictions', 'Applications & Gaming', and 'Admin'. Below the navigation menu, there are sub-tabs for 'Basic Wireless Settings', 'Wireless Security', 'Wireless MAC Filter', and 'Advanced'. The main content area is titled 'Wireless Security' and contains the following settings:

- Security Mode: WPA Personal (dropdown menu)
- Encryption: TKIP (dropdown menu)
- Passphrase: [Red highlighted text input field]
- Key Renewal: 3600 seconds (text input field)

At the bottom of the page, there are two buttons: 'Save Settings' and 'Cancel Changes'.

At time of your installation our technicians recommended Linksys brand Wireless routers. If you did not choose to use a Linksys brand wireless router we can only attempt to retrieve your wireless key. Most routers are setup very similar to this one. Please refer to your router manual for any instructions that could be different from the recommended router brand.